alpha	IMICCO	SOF	<b>TWA</b> V4.				TE
			Volun	ne II,	lunie Nựm	198 <sup>4</sup> ber 4	1
Contents of th							
INTRODUCTION	ON SYSTEM DISK COPYR			• • •	••	• •	1 1
DOCUMENTATION AMOS Monito AMOS 4.5 So	ADJUSTMENTS or Calls Manual oftware Update Docum	entation Pa					1
SOFTWARE CHANG DSKANA SYSTEM.MON	e Packet #1 for the GE NOTICES		L User's M	••••	• •	• • •	2
RESOLVED SOFT	WARE PERFORMANCE REP	PORTS			۰ ،		3

# 'Alpha Micro', 'AMOS', 'AlphaBASIC', 'AlphaPASCAL', 'AlphaLISP', and 'AlphaSERV'

əre trademarks of

ALPHA MICROSYSTEMS Irvine, CA 92714

1981 - ALPHA MICROSYSTEMS

ALPHA MICROSYSTEMS 17881 Sky Park North Irvine, CA 92714

### INTRODUCTION

This 'is the Alpha Micro <u>Software Notes</u>, a publication designed to give technical software information to our OEM/dealer network. Please address all inquiries or suggestions concerning this newsletter to:

## Editor, Alpha Micro <u>Software Notes</u> P.O. Box <u>18347</u> Irvine, CA 92713

NOTE: Because of our attention to the 4.5 and 4.5A releases, there was no May issue of the Software Notes.

First of all, we'd like to say how much we enjoyed seeing many of our dealers at NCC. We appreciate the comments and suggestions our dealers offered in person, and feel our company benefits greatly from participating in the convention.

This month's <u>Software Notes</u> is short and probably could have been combined with next month's. However, there are a few items we felt we should call to your attention promptly. First is a note concerning our System Disk copyright labels. Secondly, we alert you to added material in the <u>AMOS</u> <u>Monitor Calls Manual</u>, a correction in the <u>AMOS 4.5</u> Software Update <u>Documentation Packet</u>, and a correction in <u>Change Page Packet #1 for the</u> <u>"AlphaPascal User's Manual"</u>. Next, we provide a patch to the DSKANA program in the SOFTWARE CHANGE NOTICES section. Finally, those of you who have sent in Software Performance Reports (SPR) since the last release will be 'interested in the RESOLVED SOFTWARE PERFORMANCE REPORTS section. We have listed all SPRs, by SPR number, that have been resolved for the 4.5 release. You will soon receive a follow-up letter detailing how the SPR you sent in was resolved.

#### SPECIAL NOTE

In the past, you may have noticed that copyright labels for the AMOS system are included in Volume 1 of the Alpha Micro Software Documentation Library. It is extremely important that you place these labels on all copies of the AMOS System Disk that you generate. Also, please inform your end users that they should put these labels on their copies of the System Disk.

#### DOCUMENTATION ADJUSTMENTS

# The Monitor Calls Manual

1

In the recent rewrite of the <u>AMOS Monitor Calls Manual</u> (DWM-00100-42), we introduced PCALL and <u>AMOS</u> in Chapter 10. Change pages concerning these calls will be available shortly, but we want you to have the following additional information now:

You cannot use the PCALL or AMOS monitor call to execute a program if that program locates its stack area in the user partition. For example, using PCALL or AMOS to invoke AlphaVUE does not work because VUE sets up a stack in the user partition, which wipes out information stored by either monitor call.

## The AMOS 4.5 Software Update Documentation

Some of you have already received or will soon receive the AMOS 4.5 Software Update Documentation Packet. We wish to point out that our printers made an error in collation. Near the end of the "System Operator's Information" section are 'two documents: Using the Magnetic Tape Utility Programs and The Magnetic Tape File Backup Programs. The pages of these two documents are out of order. To correct the error, simply look at the document title and the page number at the top of each page to determine how the two documents should be collated.

## Change Page Packet #1 for the "AlphaPASCAL User's Manual"

Two change bars appear on page 5-3 of this change page packet. Each of the marked lines should contain a period alone on the line. Because of a printing error, these dots did not appear in the printed copies of the change page packet. However, they are <u>VERY</u> important, so please draw them REMEMBER: Every AlphaPASCAL module file must end with a period, even in. though it cannot end with the END keyword.

## SOFTWARE CHANGE NOTICES

This month we have a patch to the 4.5 DSKANA program and the usual patch that updates the monitor version number.

### DSKANA

1 3

When you specify a switch at the end of the DSKANA command line, incorrect entry of the slash or any extra characters after the specification of the device to: be; analyzed causes the program to enter an endless loop, suspending the job. The following patch prevents this endless loop.

.DIR/H DSKANA (RET)	
DSKANA PRG 9 737-7	27-232-054 DSK0:[1,4]
DDT DSKANA (RET)	
PROGRAM BASE IS XXXXXX	
PROGRAM SIZE IS 10526	
1566	
15567 CMPB @R2,#57	CALL PC,7776 🕹
1572/ BNE 1600	117↓
1574/ CALL 7776	BEQ 1602
1576/ · NEG @117(SP)	JMP 1361
1602/ BNE 1566	0
<u>^C</u>	
DIR MEM: DSKANA/H RET	
DSKANA PRG 4438	046-372-325-456 MEM:
.SAVE DSKANA.PRG (RET)	
ERASE DSKANA.PRG,	SAVE DSKANA.PRG
<u> </u>	

## SYSTEM.MON

This patch updates the version of your monitor, indicating that you have performed the DSKANA patch shown above.

Whenever you use the SYSTAT or SYSTEM command, you see a line showing your current monitor version. If you are now running on AMOS Version 4.5, the line should show version 4.5. The following patch changes this line to show 4.5(1), indicating that you have implemented the patch in this issue of <u>Software Notes</u>. That means you should not enter this patch until you have entered the previous patch. This patch does not affect the operation of the monitor; it just gives you a quick way to see if all patches, have been implemented.

If this patch is used with a version previous to the 4.5 monitor, the change will not show up. We assume you will update to AMOS version 4.5 before implementing any patches.

The patch is as follows:

LOG SYS: RET Logged into SYS: DDT SYSTEM.MON RET

PROGRAM BASE IS XXXXX PROGRAM SIZE IS 34174

.SAVE SYSTEM.MON RET

#### RESOLVED SOFTWARE PERFORMANCE REPORTS

24065 🕹

24491 1

Following is a list of the programs that we changed for release 4.5 as a result of SPRs sent in. We also include the SPR numbers, so that those of you who sent in the SPRs can update your own files.

210DVR.DVR

i

SPRs: 2423, 4322, 2458

APPEND

ł

SPRs: 2035, 2147, 2543

## ALphaBASIC V4.5 (BASIC, COMPIL, RUN, RUNSML)

SPRs: 2426, 2539, 2354, 2428, 2548, 1584, 2087, 2146, 2178, 2501, 2385, 2167, 1663, 1609, 1546, 1847, 1778, 1776, 2327, 1007, 2291, 2504, 2441, 2049, 3772, 2387, 2296, 1882, 1970, 2148, 1746, 1501, 1171, 1115, 2530, 1914, 4923, 1750, 2290, 1769, 2375, 3596, 2604, 4410, 4324, 2502, 1121, 1807, 4839, 2850

SOFTWARE NOTES - JUNE 1981
<u>CRT410</u>
SPR: 2523
DSKANA
SPRs: 2020, 2030, 2349, 2452, 2405, 5510
DSKCPY
SPRs: 1977, 3178, 3324, 2150, 2224, 2440, 2447, 2550
DSKPAK
SPRs: 2069, 4373
GLOBAL
SPR: 2022
MACRO
SPRs: 1637, 2015, 1474
MAP
SPR: 2413
PLINK
SPR: 2372
PRINT
SPRs: 5500, 5503
SAVE
SPRs: 2230, 1712
SLEEP
SPR: 5505
SPOOL . SBR
SPRs: 1595, 2197
TAPE
SPR: 2298
TXTFMT
SPRs: 2312, 2368, 2373, 2454, 2455, 2456, 2457, 2477, 2478

Page 4